



LHC COMPUTING GRID

LCG - UI - GENERIC CONFIGURATION REFERENCE

<i>Document identifier:</i>	LCG-GIS-CR-UI
<i>EDMS id:</i>	none
<i>Version:</i>	
<i>Date:</i>	January 16, 2006
<i>Section:</i>	LCG Grid Infrastructure Support
<i>Document status:</i>	ACTIVE
<i>Author(s):</i>	Keeble, Oliver; LCG Deployment - GIS team; Retico, Antonio; Vidic, Valentin;
<i>File:</i>	UI

Abstract: Configuration steps done by the YAIM script 'configure_UI'



CONTENTS

1. INTRODUCTION	4
2. VARIABLES	5
3. CONFIGURE LIBRARY PATHS	7
3.1. SPECIFICATION OF FUNCTION: CONFIG_LDCONF	7
4. SET-UP EDG CONFIGURATION VARIABLES	8
4.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_EDG	8
5. SET-UP GLOBUS CONFIGURATION VARIABLES	9
5.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_GLOBUS	9
6. SET-UP LCG CONFIGURATION VARIABLES	10
6.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_LCG	10
7. SET-UP UPDATING OF CRLS	11
7.1. SPECIFICATION OF FUNCTION: CONFIG_CRL	11
8. SET-UP RFIO	12
8.1. SPECIFICATION OF FUNCTION: CONFIG_RFIO.....	12
9. SET-UP GLOBUS DAEMONS	13
9.1. SPECIFICATION OF FUNCTION: CONFIG_GLOBUS	13
10. SET-UP LCG ENVIRONMENT VARIABLES	15
10.1. SPECIFICATION OF FUNCTION: CONFIG_LCGENV	17
11. SET-UP REPLICA MANAGER	18
11.1. SPECIFICATION OF FUNCTION: CONFIG_REPLICA_MANAGER	18
12. SET-UP JAVA LOCATION	19
12.1. SPECIFICATION OF FUNCTION: CONFIG_JAVA.....	19
13. SET-UP R-GMA CLIENT	20
13.1. SPECIFICATION OF FUNCTION: CONFIG_RGMA_CLIENT	20
14. SET-UP WORKLOAD MANAGER CLIENT	21
14.1. SPECIFICATION OF FUNCTION: CONFIG_WORKLOAD_MANAGER_CLIENT.....	22
15. CONFIGURE THE VOMSES FILES	23
15.1. SPECIFICATION OF FUNCTION: CONFIG_VOMSES	23
16. SET-UP FILE TRANSFER SERVICE CLIENT	24
16.1. SPECIFICATION OF FUNCTION: CONFIG_FTS_CLIENT	24



17. SET-UP GLITE ENVIRONMENT	25
17.1. SPECIFICATION OF FUNCTION: CONFIG_GLITE_ENV	25
18. SET-UP GSI ENABLED SSH	27
18.1. SPECIFICATION OF FUNCTION: CONFIG_GSISSH	27
19. SOURCE CODE	28
19.1. CONFIG_LDCONF.....	28
19.2. CONFIG_SYSCONFIG_EDG	28
19.3. CONFIG_SYSCONFIG_GLOBUS.....	29
19.4. CONFIG_SYSCONFIG_LCG.....	29
19.5. CONFIG_CRL.....	30
19.6. CONFIG_RFIO	31
19.7. CONFIG_GLOBUS.....	31
19.8. CONFIG_LCGENV.....	35
19.9. CONFIG_REPLICA_MANAGER	39
19.10. CONFIG_JAVA	40
19.11. CONFIG_RGMA_CLIENT	41
19.12. CONFIG_WORKLOAD_MANAGER_CLIENT	43
19.13. CONFIG_VOMSES.....	45
19.14. CONFIG_FTS_CLIENT	45
19.15. CONFIG_GLITE_ENV.....	46
19.16. CONFIG_GSISSH.....	48



1. INTRODUCTION

This document lists the manual steps for the installation and configuration of a LCG UI Node. Furthermore it provides a specification of the YAIM functions used to configure the node with the script-based configuration.

The configuration has been tested on a standard Scientific Linux 3.0 Installation.

Link to this document:

This document is available on the *Grid Deployment* web site

<http://www.cern.ch/grid-deployment/gis/lcg-GCR/index.html>



2. VARIABLES

In order to set-up a UI node, you need at least the following variables to be correctly configured in the site configuration file (site-info.def):

BDII_HOST : BDII Hostname.

CE_HOST : Computing Element Hostname.

DPM_HOST : Host name of the DPM host, used also as a default DPM for the lcg-stdout-mon .

EDG_WL_SCRATCH : Optional scratch directory for jobs.

EDG_WL_SCRATCH : Optional scratch directory for jobs.

FTS_SERVER_URL : URL of the File Transfer Service server.

GLOBUS_TCP_PORT_RANGE : Port range for Globus IO.

GRIDICE_SERVER_HOST : GridIce server host name (usually run on the MON node).

GSSKLOG : yes or no, indicating whether the site provides an AFS authentication server which maps gsi credentials into Kerberos tokens .

GSSKLOG_SERVER : If GSSKLOG is yes, the name of the AFS authentication server host.

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

JAVA_LOCATION : Path to Java VM installation. It can be used in order to run a different version of java installed locally.

JOB_MANAGER : The name of the job manager used by the gatekeeper.

MON_HOST : MON Box Hostname.

OUTPUT_STORAGE : Default Output directory for the jobs.

PX_HOST : PX hostname.

RB_HOST : Resource Broker Hostname.

REG_HOST : RGMA Registry hostname.

SE_LIST : A list of hostnames of the SEs available at your site.

SITE_NAME : Your GIIS.

VOBOX_HOST : VOBOX hostname.

VOBOX_PORT : The port the VOBOX gsisshd listens on.



VOS : List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:

VO_<VO-NAME>_SE : Default SE used by the VO. WARNING: VO-NAME must be in capital cases.

VO_<VO-NAME>_SW_DIR : Area on the WN for the installation of the experiment software. If on the WNs a predefined shared area has been mounted where VO managers can pre-install software, then these variable should point to this area. If instead there is not a shared area and each job must install the software, then this variables should contain a dot (.). Anyway the mounting of shared areas, as well as the local installation of VO software is not managed by *yaim* and should be handled locally by Site Administrators. WARNING: VO-NAME must be in capital cases.

VO_<VO-NAME>_VOMSES : List of entries for the vomses files for this VO. Multiple values can be given if enclosed in single quotes.



3. CONFIGURE LIBRARY PATHS

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function *'config_ldconf'*.

In order to allow the middleware libraries to be looked up and dynamically linked, the relevant paths need to be configured.

- If not already there, append the following lines to the file */etc/ld.so.conf*

```
<INSTALL_ROOT>/globus/lib
<INSTALL_ROOT>/edg/lib
<INSTALL_ROOT>/lcg/lib
/usr/local/lib
/usr/kerberos/lib
/usr/X11R6/lib
/usr/lib/qt-3.1/lib
/opt/gcc-3.2.2/lib
```

where *<INSTALL_ROOT>* is the installation root of the lcg middleware (*/opt* by default).

- Run the command:

```
> /sbin/ldconfig -v
```

(this command produces a huge amount of output)

3.1. SPECIFICATION OF FUNCTION: CONFIG_LDCONF

The function *'config_ldconf'* needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_ldconf
```

The code is reproduced also in 19.1..



4. SET-UP EDG CONFIGURATION VARIABLES

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_sysconfig_edg*'.

The EDG configuration file is parsed by EDG daemons to locate the EDG root directory and various other global properties.

Create and edit the file */etc/sysconfig/edg* as follows:

```
EDG_LOCATION=<INSTALL_ROOT>/edg
EDG_LOCATION_VAR=<INSTALL_ROOT>/edg/var
EDG_TMP=/tmp
X509_USER_CERT=/etc/grid-security/hostcert.pem
X509_USER_KEY=/etc/grid-security/hostkey.pem
GRIDMAP=/etc/grid-security/grid-mapfile
GRIDMAPDIR=/etc/grid-security/gridmapdir/
```

where *<INSTALL_ROOT>* is the installation root of the lcg middleware (*/opt* by default).

NOTE: it might be observed that some of the variables above listed dealing with the GSI (Grid Security Interface) are needed just on service nodes (e.g. CE, RB) and not on others. Nevertheless, for sake of simplicity, *yaim* uses the same definitions on all node types, which has been proven not to hurt.

4.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_EDG

The function '*config_sysconfig_edg*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_sysconfig_edg
```

The code is reproduced also in 19.2..



5. SET-UP GLOBUS CONFIGURATION VARIABLES

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_sysconfig_globus*'.

Create and edit the file */etc/sysconfig/globus* as follows:

```
GLOBUS_LOCATION=<INSTALL_ROOT>/globus
GLOBUS_CONFIG=/etc/globus.conf
GLOBUS_TCP_PORT_RANGE="20000 25000"
export LANG=C
```

where *<INSTALL_ROOT>* is the installation root of the lcg middleware (*/opt* by default).

5.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_GLOBUS

The function '*config_sysconfig_globus*' needs the following variables to be set in the configuration file:

GLOBUS_TCP_PORT_RANGE : Port range for Globus IO.

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_sysconfig_globus
```

The code is reproduced also in 19.3..



6. SET-UP LCG CONFIGURATION VARIABLES

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_sysconfig_lcg*'.

Create and edit the file */etc/sysconfig/lcg* as follows:

```
LCG_LOCATION=<INSTALL_ROOT>/lcg
LCG_LOCATION_VAR=<INSTALL_ROOT>/lcg/var
LCG_TMP=/tmp
```

where *<INSTALL_ROOT>* is the installation root of the *lcg* middleware (*/opt* by default).

6.1. SPECIFICATION OF FUNCTION: CONFIG_SYSCONFIG_LCG

The function '*config_sysconfig_lcg*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

SITE_NAME : Your GIIS.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_sysconfig_lcg
```

The code is reproduced also in 19.4..



7. SET-UP UPDATING OF CRLS

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_crl*'.

Cron script is installed to fetch new versions of CRLs four times a day. The time when the script is run is randomized in order to distribute the load on CRL servers. If the configuration is run as root, the cron entry is installed in */etc/cron.d/edg-fetch-crl*, otherwise it is installed as a user cron entry.

CRLs are also updated immediately by running the update script (*<INSTALL_ROOT>/edg/etc/cron/edg-fetch-crl-cron*).

Logrotate script is installed as */etc/logrotate.d/edg-fetch-crl* to prevent the logs from growing indefinitely.

7.1. SPECIFICATION OF FUNCTION: CONFIG_CRL

The function '*config_crl*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_crl`

The code is reproduced also in 19.5..



8. SET-UP RFIO

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_rfio*'.

rfiod is configured on SE_classic nodes by adding the appropriate ports (5001 TCP and UDP) to */etc/services* and restarting the daemon.

For SE_dpm nodes, *rfiod* is configured by *config_DPM_rfio* so no configuration is done here.

All other nodes don't run *rfiod*. However, *rfiod* might still be installed from *CASTOR-client* RPM. If this is the case, we make sure it's stopped and disabled.

8.1. SPECIFICATION OF FUNCTION: CONFIG_RFIO

The function '*config_rfio*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_rfio`

The code is reproduced also in 19.6..



9. SET-UP GLOBUS DAEMONS

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_globus*'.

The Globus configuration file */etc/globus.conf* is parsed by Globus daemon startup scripts to locate the Globus root directory and other global/daemon specific properties. The contents of the configuration file depend on the type of the node. The following table contains information on daemon to node mapping:

node/daemon	MDS	GridFTP	Gatekeeper
CE	yes	yes	yes
VOBOX	yes	yes	yes
SE_*	yes	yes	no
SE_dpm	yes	no	no
PX	yes	no	no
RB	yes	no	no
LFC	yes	no	no
GridICE	yes	no	no

Note that SE_dpm does not run standard GridFTP server, but a specialized DPM version.

The configuration file is divided into sections:

common Defines Globus installation directory, host certificates, location of gridmap file etc.

mds Defines information providers.

gridftp Defines the location of the GridFTP log file.

gatekeeper Defines jobmanagers and their parameters.

Logrotate scripts *globus-gatekeeper* and *gridftp* are installed in */etc/logrotate.d/*.

Globus initialization script (*<INSTALL_DIR>/globus/sbin/globus-initialization.sh*) is run next.

Finally, the appropriate daemons (*globus-mds*, *globus-gatekeeper*, *globus-gridftp*, *lcg-mon-gridftp*) are started (and configured to start on boot).

9.1. SPECIFICATION OF FUNCTION: CONFIG_GLOBUS

The function '*config_globus*' needs the following variables to be set in the configuration file:

CE_HOST : Computing Element Hostname.

GRIDICE_SERVER_HOST : GridIce server host name (usually run on the MON node).



INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

JOB_MANAGER : The name of the job manager used by the gatekeeper.

PX_HOST : PX hostname.

RB_HOST : Resource Broker Hostname.

SITE_NAME : Your GIIS.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_globus`

The code is reproduced also in 19.7..



10. SET-UP LCG ENVIRONMENT VARIABLES

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_lcgenv*'.

The LCG middleware needs some environment variables to be set up at boot time. The variable should be available both in 'bash-like' shells and in 'csh-like' shells.

This can be obtained in different ways:

The simplest way, if you have 'root' permissions, is to put a shell script for each of the supported shell 'families' in the directory */etc/profile.d*. The script will be automatically sourced at start up.

If instead you are not a superuser and you are doing the installation in a private directory (e.g. you are installing a Re-locatable Distribution of a Worker Node or a User Interface in the *<INSTALL_ROOT>* directory), you could create the scripts in the directory *<INSTALL_ROOT>/etc/profile.d*, in order to have the variables automatically set up by LCG tools.

The list of the environment variables to be set up follows:

LCG_GFAL_INFOSYS: Hostname of the BDII node.

MYPROXY_SERVER: Hostname of the Proxy server.

PATH: Add to the PATH variable the path */opt/d-cache-client/bin*

LD_LIBRARY_PATH: Add to the LD_LIBRARY_PATH variable the path */opt/d-cache-client/dcap*

SRM_PATH: Installation directory of the srm client. The default value for this variable is */opt/d-cache-client/srm*

VO_<VO-NAME>_SW_DIR: For each virtual organization <VO-NAME> An environment variable VO_<VO-NAME>_SW_DIR is needed. This variable points to the installation directory of the VO software.

VO_<VO-NAME>_DEFAULT_SE: For each virtual organization <VO-NAME> An environment variable VO_<VO-NAME>_DEFAULT_SE is needed. This variable points to the Default Storage Element for that VO.

The examples given hereafter refer to the simple configuration method described above. In the following description we will refer to the two possible locations as to the *<LCG_ENV_LOC>*. So, according to the cases above described, either

<LCG_ENV_LOC>=/etc/profile.d



or

`<LCG_ENV_LOC>=<INSTALL_ROOT>/etc/profile.d`

Examples:

- Example of file `<LCG_ENV_LOC>/lcgen.sh`:

```
#!/bin/sh
export LCG_GFAL_INFOSYS=lxbl769.cern.ch:2170
export MYPROXY_SERVER=lxbl774.cern.ch
export PATH="${PATH}:/opt/d-cache-client/bin"
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:/opt/d-cache-client/dcap
export SRM_PATH=/opt/d-cache-client/srm
export VO_ATLAS_SW_DIR=lxbl780.cern.ch
export VO_ATLAS_DEFAULT_SE=lxbl780.cern.ch
export VO_ALICE_SW_DIR=lxbl780.cern.ch
export VO_ALICE_DEFAULT_SE=lxbl780.cern.ch
export VO_LHCB_SW_DIR=lxbl780.cern.ch
export VO_LHCB_DEFAULT_SE=lxbl780.cern.ch
export VO_CMS_SW_DIR=lxbl780.cern.ch
export VO_CMS_DEFAULT_SE=lxbl780.cern.ch
export VO_DTEAM_SW_DIR=lxbl780.cern.ch
export VO_DTEAM_DEFAULT_SE=lxbl780.cern.ch
```

- Example of file `<LCG_ENV_LOC>/lcgen.csh`:

```
#!/bin/csh
setenv LCG_GFAL_INFOSYS lxbl769.cern.ch:2170
setenv MYPROXY_SERVER lxbl774.cern.ch
setenv PATH "${PATH}:/opt/d-cache-client/bin"
setenv LD_LIBRARY_PATH ${LD_LIBRARY_PATH}:/opt/d-cache-client/dcap
setenv SRM_PATH /opt/d-cache-client/srm
setenv VO_ATLAS_SW_DIR lxbl780.cern.ch
setenv VO_ATLAS_DEFAULT_SE lxbl780.cern.ch
setenv VO_ALICE_SW_DIR lxbl780.cern.ch
setenv VO_ALICE_DEFAULT_SE lxbl780.cern.ch
setenv VO_LHCB_SW_DIR lxbl780.cern.ch
setenv VO_LHCB_DEFAULT_SE lxbl780.cern.ch
setenv VO_CMS_SW_DIR lxbl780.cern.ch
setenv VO_CMS_DEFAULT_SE lxbl780.cern.ch
setenv VO_DTEAM_SW_DIR lxbl780.cern.ch
setenv VO_DTEAM_DEFAULT_SE lxbl780.cern.ch
```

WARNING: The two scripts must be executable by all users.

```
> chmod a+x ${LCG_ENV_LOC}/lcgen.csh
> chmod a+x ${LCG_ENV_LOC}/lcgen.sh
```




10.1. SPECIFICATION OF FUNCTION: CONFIG_LCGENV

The function '*config_lcgen*' needs the following variables to be set in the configuration file:

BDII_HOST : BDII Hostname.

CE_HOST : Computing Element Hostname.

DPM_HOST : Host name of the DPM host, used also as a default DPM for the *lcg-stdout-mon* .

EDG_WL_SCRATCH : Set this if you want jobs to use a particular scratch area.

EDG_WL_SCRATCH : Set this if you want jobs to use a particular scratch area.

GLOBUS_TCP_PORT_RANGE : Port range for Globus IO.

GSSKLOG : yes or no, indicating whether the site provides an AFS authentication server which maps gsi credentials into Kerberos tokens .

GSSKLOG_SERVER : If GSSKLOG is yes, the name of the AFS authentication server host.

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

PX_HOST : PX hostname.

SE_LIST : A list of hostnames of the SEs available at your site.

SITE_NAME : Your GIIS.

VOBOX_HOST : VOBOX hostname.

VOS : List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:

VO_<VO-NAME>_SE : Default SE used by the VO. WARNING: VO-NAME must be in capital cases.

VO_<VO-NAME>_SW_DIR : Area on the WN for the installation of the experiment software. If on the WNs a predefined shared area has been mounted where VO managers can pre-install software, then these variable should point to this area. If instead there is not a shared area and each job must install the software, then this variables should contain a dot (.). Anyway the mounting of shared areas, as well as the local installation of VO software is not managed by *yaim* and should be handled locally by Site Administrators. WARNING: VO-NAME must be in capital cases.

The function does exit with return code 1 if they are not set.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_lcgen`

The code is reproduced also in 19.8..



11. SET-UP REPLICA MANAGER

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_replica_manager*'.

Variable substitutions are generated in `<INSTALL_ROOT>/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local`:

```
@EDG.LOCATION@|<INSTALL_ROOT>/edg|location of edg middleware
@LOCALDOMAIN@|<domain>|the local domain
@DEFAULT.SE@|<SE_HOST>|the host of the close SE
@DEFAULT.CE@|<CE_HOST>|the host of the close CE
@INFOSERVICE@|MDS|The info provider to use. It can be Stub, MDS or RGMA
@RLS.MODE@|LrcOnly|The mode the RLS should be run in. LrcOnly or WithRli
@STUBFILE@||The properties file for the static file - only needed in Stub mode
@MDS.HOST@|<BDII_HOST>|The host of the MDS info provider
@MDS.PORT@|2170|The port of the MDS info provider
@ROS.FAILURE@|false|Fail if no ROS is available
@CONF.GCC@|_gcc3_2_2|The gcc suffix as used on the build box (empty for 2.95, _gcc3_2_2 for 3.2.)
@IGNORE.PREFIX@|true|Whether the RM will ignore the lfn and guid prefix.
@GRIDFTP.DCAU@|false|Does GridFTP use Data Channel Authentication (DCAU)
@GRIDFTP.STREAMS.SMALL@|1|The default number of stream to use for a small file
@GRIDFTP.STREAMS.BIG@|3|The default number of stream to use for a big file
@GRIDFTP.FILESIZE.THRESHOLD@|100|The Threshold (in MB) above which a file to transfer is considered "big"
```

The value of `<domain>` is determined by running *hostname -d*. Using these substitutions and templates in `<INSTALL_ROOT>/edg/etc/edg-replica-manager/`, Replica Manager is configured by generating files in `<EDG_LOCATION>/var/etc/edg-replica-manager`:

```
<INSTALL_ROOT>/edg/sbin/edg-replica-manager-configure <INSTALL_ROOT>/edg/etc/edg-replica-manager/edg-replica-manage
```

11.1. SPECIFICATION OF FUNCTION: CONFIG_REPLICA_MANAGER

The function '*config_replica_manager*' needs the following variables to be set in the configuration file:

BDII_HOST : BDII Hostname.

CE_HOST : Computing Element Hostname.

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

SE_LIST : A list of hostnames of the SEs available at your site.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_replica_manager
```

The code is also reproduced in 19.9..



12. SET-UP JAVA LOCATION

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_java*'.

Since Java is not included in the LCG distribution, Java location needs to be configured with *yaim*.

If `<JAVA_LOCATION>` is not defined in *site-info.def*, it is determined from installed Java RPMs (if available).

In relocatable distribution, `JAVA_HOME` environment variable is defined in `<INSTALL_ROOT>/etc/profile.d/grid_en` and `<INSTALL_ROOT>/etc/profile.d/grid_env.csh`.

Otherwise, `JAVA_HOME` is defined in `/etc/java/java.conf` and `/etc/java.conf` and Java binaries added to `PATH` in `<INSTALL_ROOT>/edg/etc/profile.d/j2.sh` and `<INSTALL_ROOT>/edg/etc/profile.d/j2.csh`.

12.1. SPECIFICATION OF FUNCTION: CONFIG_JAVA

The function '*config_java*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

JAVA_LOCATION : Path to Java VM installation. It can be used in order to run a different version of java installed locally.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_java
```

The code is reproduced also in 19.10..



13. SET-UP R-GMA CLIENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_rgma_client*'.

R-GMA client configuration is generated in `<INSTALL_ROOT>/glite/etc/rgma/rgma.conf` by running:

```
<INSTALL_ROOT>/glite/share/rgma/scripts/rgma-setup.py --secure=no --server=<MON_HOST> --registry=<REG_HOST> --scheme=<SCHEME>
```

`<INSTALL_ROOT>/edg/etc/profile.d/edg-rgma-env.sh` and `<INSTALL_ROOT>/edg/etc/profile.d/edg-rgma-env.csh` with the following functionality:

- `RGME_HOME` is set to `<INSTALL_ROOT>/glite`
- `APEL_HOME` is set to `<INSTALL_ROOT>/glite`
- `<INSTALL_ROOT>/glite/lib/python` is added to `PYTHONPATH`
- `<INSTALL_ROOT>/glite/lib` is added to `LD_LIBRARY_PATH`.

These files are sourced into the users environment from `<INSTALL_ROOT>/etc/profile.d/z_edg_profile.sh` and `<INSTALL_ROOT>/etc/profile.d/z_edg_profile.csh`.

13.1. SPECIFICATION OF FUNCTION: CONFIG_RGMA_CLIENT

The function '*config_rgma_client*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

MON_HOST : MON Box Hostname.

REG_HOST : RGMA Registry hostname.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_rgma_client
```

The code is also reproduced in 19.11..



14. SET-UP WORKLOAD MANAGER CLIENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_workload_manager_client*'.

For each of the supported VOs, a configuration file is generated in `<INSTALL_ROOT>/edg/etc/<vo>/edg_wl_ui.conf`:

```
[
VirtualOrganisation = "<vo>";
NSAddresses = "<RB_HOST>:7772";
LBAddresses = "<RB_HOST>:9000";
## HLR location is optional. Uncomment and fill correctly for
## enabling accounting
#HLRLocation = "fake HLR Location"
## MyProxyServer is optional. Uncomment and fill correctly for
## enabling proxy renewal. This field should be set equal to
## MYPROXY_SERVER environment variable
MyProxyServer = "<PX_HOST>"
]
```

This file defines RB and MyProxy server to be used for a specific VO.

Defaults common to all VOs are defined in `<INSTALL_ROOT>/edg/etc/edg_wl_ui_cmd_var.conf`:

```
[
rank = - other.GlueCEStateEstimatedResponseTime;
requirements = other.GlueCEStateStatus == "Production";
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "<OUTPUT_STORAGE>";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "<RB_HOST>:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
```

and `<INSTALL_ROOT>/edg/etc/edg_wl_ui_gui_var.conf`:

```
[
JDLEDefaultSchema = "Glue";
Glue = [
rank = - other.GlueCEStateEstimatedResponseTime;
rankMPI = other.GlueCEStateFreeCPUs;
requirements = other.GlueCEStateStatus == "Production"
]
```



```
];
EDG = [
rank = - other.EstimatedTraversalTime;
rankMPI = other.FreeCPUs;
requirements = true
];
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "<OUTPUT_STORAGE>";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "<RB_HOST>:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
```

Directory for storing job output sandboxes (<OUTPUT_STORAGE>) is created.

Finally, *edg-wl-ui-env.csh*, *edg-wl-ui-env.sh*, *edg-wl-ui-gui-env.csh* and *edg-wl-ui-gui-env.sh* are copied from <INSTALL_ROOT>/edg/etc/profile.d/ to <INSTALL_ROOT>/edg/var/etc/profile.d. These scripts are sourced from /etc/profile.d and are used to setup the environment for EDG programs.

14.1. SPECIFICATION OF FUNCTION: CONFIG_WORKLOAD_MANAGER_CLIENT

The function '*config_workload_manager_client*' needs the following variables to be set in the configuration file:

INSTALL_ROOT : Installation root - change if using the re-locatable distribution.

OUTPUT_STORAGE : Default Output directory for the jobs.

PX_HOST : PX hostname.

RB_HOST : Resource Broker Hostname.

VOS : List of supported VOs.

The original code of the function can be found in:

/opt/lcg/yaim/functions/config_workload_manager_client

The code is also reproduced in 19.12..



15. CONFIGURE THE VOMSES FILES

Author(s): Keeble, Oliver

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config_vomses*'.

This function creates the vomses configuration files. Each file contains one line of information describing a VOMS server. This information is used by commands like *voms-proxy-init* in order to create a voms proxy. The necessary information is taken from parameters in *site-info.def* (*VO_XXX_VOMSES*).

The files are placed in central directories if run as root, or in *.edg/vomses* if run as a user.

15.1. SPECIFICATION OF FUNCTION: CONFIG_VOMSES

The function 'config_vomses' needs the following variables to be set in the configuration file:

INSTALL_ROOT : *Installation root - change if using the re-locatable distribution.*

VOS : *List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:*

VO_<VO-NAME>_VOMSES : *List of entries for the vomses files for this VO. Multiple values can be given if enclosed in single quotes.*

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_vomses`

The code is also reproduced in 19.13..



16. SET-UP FILE TRANSFER SERVICE CLIENT

Author(s): Vidic,Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the yaim function 'config_fts_client'.

If <FTS_SERVER_URL> is set, gLite FTS client is configured by creating <INSTALL_ROOT>/glite/etc/services.xml.

```
<services>

<service name="EGEEfts">
  <parameters>
    <endpoint><FTS_SERVER_URL>/services/FileTransfer</endpoint>
    <type>org.glite.FileTransfer</type>
    <version>3.0.0</version>
  </parameters>
</service>

<service name="EGEEchannel">
  <parameters>
    <endpoint><FTS_SERVER_URL>/services/ChannelManagement</endpoint>
    <type>org.glite.ChannelManagement</type>
    <version>3.0.0</version>
  </parameters>
</service>

</services>
```

16.1. SPECIFICATION OF FUNCTION: CONFIG_FTS_CLIENT

The function 'config_fts_client' needs the following variables to be set in the configuration file:

FTS_SERVER_URL : *URL of the File Transfer Service server.*

INSTALL_ROOT : *Installation root - change if using the re-locatable distribution.*

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_fts_client`

The code is also reproduced in 19.14..



17. SET-UP GLITE ENVIRONMENT

Author(s): Vidic,Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the yaim function 'config_glite_env'.

/etc/profile.d/gliteenv.sh and /etc/profile.d/gliteenv.csh are created. These scripts set environment variables needed to run gLite programs, for example /etc/profile.d/gliteenv.sh:

```
if test "x${LCG_ENV_SET+x}" = x; then

    GLITE_LOCATION=${GLITE_LOCATION:-/opt/glite}
    GLITE_LOCATION_VAR=${GLITE_LOCATION_VAR:-$GLITE_LOCATION/var}
    GLITE_LOCATION_LOG=${GLITE_LOCATION_LOG:-$GLITE_LOCATION/log}
    GLITE_LOCATION_TMP=${GLITE_LOCATION_TMP:-$GLITE_LOCATION/tmp}

    if [ -z "$PATH" ]; then
        PATH="${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
    else
        PATH="${PATH}:${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
    fi

    if [ -z "$LD_LIBRARY_PATH" ]; then
        LD_LIBRARY_PATH="${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    else
        LD_LIBRARY_PATH="${LD_LIBRARY_PATH}:${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    fi

    if [ -z "$PERLLIB" ]; then
        PERLLIB="${GLITE_LOCATION}/lib/perl5"
    else
        PERLLIB="${PERLLIB}:${GLITE_LOCATION}/lib/perl5"
    fi

    if [ -z "$MANPATH" ]; then
        MANPATH="${GLITE_LOCATION}/share/man"
    else
        MANPATH="${MANPATH}:${GLITE_LOCATION}/share/man"
    fi

    export GLITE_LOCATION GLITE_LOCATION_VAR GLITE_LOCATION_LOG GLITE_LOCATION_TMP PATH LD_LIBRARY_PATH PERLLIB MANPATH

fi
```

/etc/profile.d/gliteenv.csh has the same functionality but for CSH compatible shells.

17.1. SPECIFICATION OF FUNCTION: CONFIG_GLITE_ENV

The function 'config_glite_env' needs the following variables to be set in the configuration file:

INSTALL_ROOT : *Installation root - change if using the re-locatable distribution.*



The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_glite_env`

The code is also reproduced in 19.15..



18. SET-UP GSI ENABLED SSH

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the yaim function 'config_gsissh'.

First, the generic configuration script (<INSTALL_ROOT>/globus/setup/gsi_openssh_setup/setup_openssh) is run (if it exists). It will generate host keys and a default configuration.

At the moment, further configuration is only done for VOBOX nodes.

Configuration files for SSH daemon and client are modified to use GSI authentication. All other authentication types and root login are disabled for the daemon.

The startup script is modified to make the gsisshd listen on a nondefault port (<VOBOX_PORT>). It is then installed as /etc/init.d/gsisshd. The gsisshd daemon is restarted and configured to start on boot.

18.1. SPECIFICATION OF FUNCTION: CONFIG_GSISSH

The function 'config_gsissh' needs the following variables to be set in the configuration file:

INSTALL_ROOT : *Installation root - change if using the re-locatable distribution.*

VOBOX_PORT : *The port the VOBOX gsisshd listens on.*

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_gsissh`

The code is also reproduced in 19.16..



19. SOURCE CODE

19.1. CONFIG_LDCONF

```
config_ldconf () {  
  
    INSTALL_ROOT=${INSTALL_ROOT:-/opt}  
  
    cp -p /etc/ld.so.conf /etc/ld.so.conf.orig  
  
    LIBDIRS="${INSTALL_ROOT}/globus/lib \  
    ${INSTALL_ROOT}/edg/lib \  
        ${INSTALL_ROOT}/edg/externals/lib/ \  
    /usr/local/lib \  
        ${INSTALL_ROOT}/lcg/lib \  
        /usr/kerberos/lib \  
        /usr/X11R6/lib \  
        /usr/lib/qt-3.1/lib \  
        ${INSTALL_ROOT}/gcc-3.2.2/lib \  
        ${INSTALL_ROOT}/glite/lib \  
        ${INSTALL_ROOT}/glite/externals/lib"  
  
    if [ -f /etc/ld.so.conf.add ]; then  
rm -f /etc/ld.so.conf.add  
    fi  
  
    for libdir in ${LIBDIRS}; do  
if ( ! grep -q $libdir /etc/ld.so.conf && [ -d $libdir ] ); then  
    echo $libdir >> /etc/ld.so.conf.add  
fi  
done  
  
    if [ -f /etc/ld.so.conf.add ]; then  
sort -u /etc/ld.so.conf.add >> /etc/ld.so.conf  
rm -f /etc/ld.so.conf.add  
    fi  
  
    /sbin/ldconfig  
  
    return 0  
}
```

19.2. CONFIG_SYSCONFIG_EDG

```
config_sysconfig_edg() {  
  
    INSTALL_ROOT=${INSTALL_ROOT:-/opt}  
  
    cat <<EOF > /etc/sysconfig/edg  
EDG_LOCATION=${INSTALL_ROOT}/edg
```



```
EDG_LOCATION_VAR=$INSTALL_ROOT/edg/var
EDG_TMP=/tmp
X509_USER_CERT=/etc/grid-security/hostcert.pem
X509_USER_KEY=/etc/grid-security/hostkey.pem
GRIDMAP=/etc/grid-security/grid-mapfile
GRIDMAPDIR=/etc/grid-security/gridmapdir/
EDG_WL_BKSERVERD_ADDOPTS=--rgmaexport
EDG_WL_RGMA_FILE=/var/edgwl/logging/status.log
EOF
```

```
return 0
}
```

19.3. CONFIG_SYSCONFIG_GLOBUS

```
config_sysconfig_globus() {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

# If GLOBUS_TCP_PORT_RANGE is unset, give it a good default
# Leave it alone if it is set but empty
GLOBUS_TCP_PORT_RANGE=${GLOBUS_TCP_PORT_RANGE-"20000 25000"}

cat <<EOF > /etc/sysconfig/globus
GLOBUS_LOCATION=$INSTALL_ROOT/globus
GLOBUS_CONFIG=/etc/globus.conf
export LANG=C
EOF

# Set GLOBUS_TCP_PORT_RANGE, but not for nodes which are only WNs
if [ "$GLOBUS_TCP_PORT_RANGE" ] && ( ! echo $NODE_TYPE_LIST | egrep -q '^ *WN_*[[:alpha:]]* *$' ); then
    echo "GLOBUS_TCP_PORT_RANGE=\"$GLOBUS_TCP_PORT_RANGE\"" >> /etc/sysconfig/globus
fi

(
    # HACK to avoid complaints from services that do not need it,
    # but get started via a login shell before the file is created...

    f=$INSTALL_ROOT/globus/libexec/globus-script-initializer
    echo '' > $f
    chmod 755 $f
)

return 0
}
```

19.4. CONFIG_SYSCONFIG_LCG

```
config_sysconfig_lcg() {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}
```



```
cat <<EOF > /etc/sysconfig/lcg
LCG_LOCATION=$INSTALL_ROOT/lcg
LCG_LOCATION_VAR=$INSTALL_ROOT/lcg/var
LCG_TMP=/tmp
export SITE_NAME=$SITE_NAME
EOF
```

```
return 0
}
```

19.5. CONFIG_CRL

```
config_crl(){
```

```
INSTALL_ROOT=${INSTALL_ROOT:-/opt}
```

```
let minute="$RANDOM%60"
```

```
let h1="$RANDOM%24"
```

```
let h2="($h1+6)%24"
```

```
let h3="($h1+12)%24"
```

```
let h4="($h1+18)%24"
```

```
if !( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then
```

```
    if [ ! -f /etc/cron.d/edg-fetch-crl ]; then
```

```
echo "Now updating the CRLs - this may take a few minutes..."
```

```
$INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> /var/log/edg-fetch-crl-cron.log 2>&1
```

```
    fi
```

```
cron_job edg-fetch-crl root "$minute $h1,$h2,$h3,$h4 * * * $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> /var/log/edg-fetch-crl-cron.log 2>&1
```

```
    cat <<EOF > /etc/logrotate.d/edg-fetch
```

```
/var/log/edg-fetch-crl-cron.log {
```

```
    compress
```

```
    monthly
```

```
    rotate 12
```

```
    missingok
```

```
    ifempty
```

```
    create
```

```
}
```

```
EOF
```

```
else
```

```
    cron_job edg-fetch-crl `whoami` "$minute $h1,$h2,$h3,$h4 * * * $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> /var/log/edg-fetch-crl-cron.log 2>&1
```

```
    if [ ! -d $INSTALL_ROOT/edg/var/log ]; then
```

```
mkdir -p $INSTALL_ROOT/edg/var/log
```

```
    fi
```

```
    echo "Now updating the CRLs - this may take a few minutes..."
```

```
    $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> $INSTALL_ROOT/edg/var/log/edg-fetch-crl-cron.log 2>&1
```



```
fi
return 0
}
```

19.6. CONFIG_RFIO

```
config_rfio() {
INSTALL_ROOT=${INSTALL_ROOT:-/opt}

# This function turns rfio on where necessary and
# just as important, turns it off where it isn't necessary

if ( echo "${NODE_TYPE_LIST}" | grep -q SE_classic ); then

    if [ "x`grep rfio /etc/services | grep tcp`" = "x" ]; then
echo "rfio    5001/tcp" >> /etc/services
    fi

    if [ "x`grep rfio /etc/services | grep udp`" = "x" ]; then
echo "rfio    5001/udp" >> /etc/services
    fi

    /sbin/service rfiod restart

elif ( echo "${NODE_TYPE_LIST}" | grep -q SE_dpms ); then

    return 0

elif ( rpm -qa | grep -q CASTOR-client ); then

    /sbin/service rfiod stop
    /sbin/chkconfig --level 2345 rfiod off

fi

return 0
}
```

19.7. CONFIG_GLOBUS

```
config_globus(){
# $Id: config_globus,v 1.34 2006/01/06 13:45:51 maart Exp $

requires CE_HOST PX_HOST RB_HOST SITE_NAME

GLOBUS_MDS=no
```



```
GLOBUS_GRIDFTP=no
GLOBUS_GATEKEEPER=no

if ( echo "${NODE_TYPE_LIST}" | grep '\<'CE > /dev/null ); then
    GLOBUS_MDS=yes
    GLOBUS_GRIDFTP=yes
    GLOBUS_GATEKEEPER=yes
fi
if ( echo "${NODE_TYPE_LIST}" | grep VOBOX > /dev/null ); then
    GLOBUS_MDS=yes
    if ! ( echo "${NODE_TYPE_LIST}" | grep '\<'RB > /dev/null ); then
GLOBUS_GRIDFTP=yes
    fi
fi
if ( echo "${NODE_TYPE_LIST}" | grep '\<'SE > /dev/null ); then
    GLOBUS_MDS=yes
    GLOBUS_GRIDFTP=yes
fi
# DPM has its own ftp server
if ( echo "${NODE_TYPE_LIST}" | grep SE_dpm > /dev/null ); then
    GLOBUS_GRIDFTP=no
fi
if ( echo "${NODE_TYPE_LIST}" | grep '\<'PX > /dev/null ); then
    GLOBUS_MDS=yes
fi
if ( echo "${NODE_TYPE_LIST}" | grep '\<'RB > /dev/null ); then
    GLOBUS_MDS=yes
fi
if ( echo "${NODE_TYPE_LIST}" | grep '\<'LFC > /dev/null ); then
    GLOBUS_MDS=yes
fi
if ( echo "${NODE_TYPE_LIST}" | grep SE_dpm > /dev/null ); then
    X509_DPM1="x509_user_cert=/home/edginfo/.globus/usercert.pem"
    X509_DPM2="x509_user_key=/home/edginfo/.globus/userkey.pem"
else
    X509_DPM1=""
    X509_DPM2=""
fi
if [ "$GRIDICE_SERVER_HOST" = "`hostname -f`" ]; then
    GLOBUS_MDS=yes
fi

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

cat <<EOF > /etc/globus.conf
#####
#
# Globus configuraton.
#
#####
[common]
GLOBUS_LOCATION=${INSTALL_ROOT}/globus
globus_flavor_name=gcc32dbg
x509_user_cert=/etc/grid-security/hostcert.pem
```




```
x509_user_key=/etc/grid-security/hostkey.pem
gridmap=/etc/grid-security/grid-mapfile
gridmapdir=/etc/grid-security/gridmapdir/

EOF

if [ "$GLOBUS_MDS" = "yes" ]; then
cat <<EOF >> /etc/globus.conf

[mds]
globus_flavor_name=gcc32dbgpthr
user=edginfo
$X509_DPM1
$X509_DPM2

[mds/gris/provider/edg]

EOF

cat <<EOF >> /etc/globus.conf
[mds/gris/registration/site]
regname=$SITE_NAME
reghn=$CE_HOST

EOF
else
echo "[mds]" >> /etc/globus.conf

fi

if [ "$GLOBUS_GRIDFTP" = "yes" ]; then

    cat <<EOF >> /etc/globus.conf
[gridftp]
log=/var/log/globus-gridftp.log
EOF

    cat <<EOF > /etc/logrotate.d/gridftp
/var/log/globus-gridftp.log /var/log/gridftp-lcas_lcmaps.log {
missingok
daily
compress
rotate 31
create 0644 root root
shredscripts
}
EOF

else
echo "[gridftp]" >> /etc/globus.conf
fi

if [ "$GLOBUS_GATEKEEPER" = "yes" ]; then
```



```
if [ "x`grep globus-gatekeeper /etc/services`" = "x" ]; then
    echo "globus-gatekeeper 2119/tcp" >> /etc/services
fi

cat <<EOF > /etc/logrotate.d/globus-gatekeeper
/var/log/globus-gatekeeper.log {
nocompress
copy
rotate 1
prerotate
killall -s USR1 -e /opt/edg/sbin/edg-gatekeeper
endscript
postrotate
find /var/log/globus-gatekeeper.log.20??????????.*[0-9] -mtime +7 -exec gzip {} \;
endscript
}
EOF

cat <<EOF >> /etc/globus.conf
[gatekeeper]

default_jobmanager=fork
job_manager_path=\${GLOBUS_LOCATION}/libexec
globus_gatekeeper=\${INSTALL_ROOT}/edg/sbin/edg-gatekeeper
extra_options="\-lcas_db_file lcas.db -lcas_etc_dir \${INSTALL_ROOT}/edg/etc/lcas/ -lcasmod_dir \
\${INSTALL_ROOT}/edg/lib/lcas/ -lcmaps_db_file lcmaps.db -lcmaps_etc_dir \${INSTALL_ROOT}/edg/etc/lcmaps -lcmapsmod_d
logfile=/var/log/globus-gatekeeper.log
jobmanagers="fork \${JOB_MANAGER}"

[gatekeeper/fork]
type=fork
job_manager=globus-job-manager

[gatekeeper/\${JOB_MANAGER}]
type=\${JOB_MANAGER}

EOF
else
cat <<EOF >> /etc/globus.conf
[gatekeeper]
default_jobmanager=fork
job_manager_path=\${GLOBUS_LOCATION}/libexec

jobmanagers="fork "

[gatekeeper/fork]
type=fork
job_manager=globus-job-manager
EOF
fi

\${INSTALL_ROOT}/globus/sbin/globus-initialization.sh 2>> \${YAIM_LOG}
```



```
if [ "$GLOBUS_MDS" = "yes" ]; then
    /sbin/chkconfig globus-mds on
    /sbin/service globus-mds stop
    /sbin/service globus-mds start
fi
if [ "$GLOBUS_GATEKEEPER" = "yes" ]; then
    /sbin/chkconfig globus-gatekeeper on
    /sbin/service globus-gatekeeper stop
    /sbin/service globus-gatekeeper start
fi
if [ "$GLOBUS_GRIDFTP" = "yes" ]; then
    /sbin/chkconfig globus-gridftp on
    /sbin/service globus-gridftp stop
    /sbin/service globus-gridftp start
    /sbin/chkconfig lcg-mon-gridftp on
    /etc/rc.d/init.d/lcg-mon-gridftp restart
fi

return 0
}
```

19.8. CONFIG_LCGENV

```
config_lcgenv() {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if !( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then
    LCG_ENV_LOC=/etc/profile.d
else
    LCG_ENV_LOC=${INSTALL_ROOT}/etc/env.d
fi

requires BDII_HOST SITE_NAME CE_HOST

if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
    requires VOS VO__SW_DIR SE_LIST
fi

default_se="${SE_LIST%% *}"

if [ "$default_se" ]; then
    for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do
        if [ "x`eval echo '$VO_${VO}_DEFAULT_SE'" = "x" ]; then
            eval VO_${VO}_DEFAULT_SE=$default_se
        fi
    done
fi

##### sh #####
cat << EOF > ${LCG_ENV_LOC}/lcgenv.sh
#!/bin/sh
```



```
if test "x\${LCG_ENV_SET+x}" = x; then
export LCG_GFAL_INFOSYS=${BDII_HOST}:2170
EOF

if [ "$PX_HOST" ]; then
echo "export MYPROXY_SERVER=$PX_HOST" >> ${LCG_ENV_LOC}/lcfgenv.sh
fi

if ( echo "${NODE_TYPE_LIST}" | egrep -q 'WN|VOBOX' ); then
  if [ "$SITE_NAME" ]; then
echo "export SITE_NAME=$SITE_NAME" >> ${LCG_ENV_LOC}/lcfgenv.sh
  fi

  if [ "$SCE_HOST" ]; then
echo "export SITE_GIIS_URL=$SCE_HOST" >> ${LCG_ENV_LOC}/lcfgenv.sh
  fi
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm/bin ]; then
  echo export PATH="\${PATH}:${INSTALL_ROOT}/d-cache/srm/bin:${INSTALL_ROOT}/d-cache/dcap/bin" >> ${LCG_ENV_LOC}/lcfgenv.sh
fi

if [ -d ${INSTALL_ROOT}/d-cache/dcap/lib ]; then
  echo export LD_LIBRARY_PATH="\${LD_LIBRARY_PATH}:${INSTALL_ROOT}/d-cache/dcap/lib" >> ${LCG_ENV_LOC}/lcfgenv.sh
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm ]; then
  echo export SRM_PATH=${INSTALL_ROOT}/d-cache/srm >> ${LCG_ENV_LOC}/lcfgenv.sh
fi

if [ "$EDG_WL_SCRATCH" ]; then
  echo "export EDG_WL_SCRATCH=$EDG_WL_SCRATCH" >> ${LCG_ENV_LOC}/lcfgenv.sh
fi

for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do

  default_se=`eval echo '$VO_${VO}_DEFAULT_SE`
  if [ "$default_se" ]; then
echo "export VO_${VO}_DEFAULT_SE=$default_se" >> ${LCG_ENV_LOC}/lcfgenv.sh
  fi

  if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
sw_dir=`eval echo '$VO_${VO}_SW_DIR`
  if [ "$sw_dir" ]; then
    echo "export VO_${VO}_SW_DIR=$sw_dir" >> ${LCG_ENV_LOC}/lcfgenv.sh
  fi
fi

done

if [ "$VOBOX_HOST" ]; then
  requires GSSKLOG
  if [ "${GSSKLOG}x" == "yesx" ]; then
    requires GSSKLOG_SERVER
  fi
fi
```



```
        echo "export GSSKLOG_SERVER=$GSSKLOG_SERVER" >> ${LCG_ENV_LOC}/lcgen.sh
    fi
fi

if [ "${DPM_HOST}" ]; then
    echo "export DPNS_HOST=${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgen.sh
    echo "export DPM_HOST=${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgen.sh
fi

if [ "$GLOBUS_TCP_PORT_RANGE" ]; then
    echo "export MYPROXY_TCP_PORT_RANGE=\"${GLOBUS_TCP_PORT_RANGE/ /,}\" >> ${LCG_ENV_LOC}/lcgen.sh
fi

if ( echo $NODE_TYPE_LIST | egrep -q UI ); then
    cat << EOF >> ${LCG_ENV_LOC}/lcgen.sh
    if [ "x${X509_USER_PROXY}" = "x" ]; then
        export X509_USER_PROXY=/tmp/x509up_u${id -u}
    fi
    EOF
fi

echo fi >> ${LCG_ENV_LOC}/lcgen.sh
##### sh #####

##### csh #####
cat << EOF > ${LCG_ENV_LOC}/lcgen.csh
#!/bin/csh
if ( ! \${LCG_ENV_SET} ) then
setenv LCG_GFAL_INFOSYS $BDII_HOST:2170
EOF

if [ "$PX_HOST" ]; then
echo "setenv MYPROXY_SERVER $PX_HOST" >> ${LCG_ENV_LOC}/lcgen.csh
fi

if ( echo "${NODE_TYPE_LIST}" | egrep -q 'WN|VOBOX' ); then
    if [ "$SITE_NAME" ]; then
echo "setenv SITE_NAME $SITE_NAME" >> ${LCG_ENV_LOC}/lcgen.csh
        fi

        if [ "$SCE_HOST" ]; then
echo "setenv SITE_GIIS_URL $SCE_HOST" >> ${LCG_ENV_LOC}/lcgen.csh
            fi
        fi

if [ -d ${INSTALL_ROOT}/d-cache/srm/bin ]; then
    echo setenv PATH "\${PATH}:${INSTALL_ROOT}/d-cache/srm/bin:${INSTALL_ROOT}/d-cache/dcap/bin" >> ${LCG_ENV_LOC}/lcgen.csh
fi

if [ -d ${INSTALL_ROOT}/d-cache/dcap/lib ]; then
    echo setenv LD_LIBRARY_PATH "\${LD_LIBRARY_PATH}:${INSTALL_ROOT}/d-cache/dcap/lib" >> ${LCG_ENV_LOC}/lcgen.csh
fi
```



```
if [ -d ${INSTALL_ROOT}/d-cache/srm ]; then
    echo setenv SRM_PATH ${INSTALL_ROOT}/d-cache/srm >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ "$EDG_WL_SCRATCH" ]; then
    echo "setenv EDG_WL_SCRATCH $EDG_WL_SCRATCH" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do

    default_se=`eval echo '$VO_${VO}_DEFAULT_SE`
    if [ "$default_se" ]; then
    echo "setenv VO_${VO}_DEFAULT_SE $default_se" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi

    if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
    sw_dir=`eval echo '$VO_${VO}_SW_DIR`
    if [ "$sw_dir" ]; then
        echo "setenv VO_${VO}_SW_DIR $sw_dir" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi
    fi

done

if [ "$VOBOX_HOST" ]; then
    requires GSSKLOG
    if [ "${GSSKLOG}x" == "yesx" ]; then
        requires GSSKLOG_SERVER
        echo "setenv GSSKLOG_SERVER $GSSKLOG_SERVER" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi
fi

if [ "${DPM_HOST}" ]; then
    echo "setenv DPNS_HOST ${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.csh
    echo "setenv DPM_HOST ${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ "$GLOBUS_TCP_PORT_RANGE" ]; then
    echo "setenv MYPROXY_TCP_PORT_RANGE \"${GLOBUS_TCP_PORT_RANGE}/ ,}\" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if ( echo $NODE_TYPE_LIST | egrep -q UI ); then
    cat << EOF >> ${LCG_ENV_LOC}/lcgenenv.csh
    if ( ! \?X509_USER_PROXY ) then
        setenv X509_USER_PROXY /tmp/x509up_u`id -u`\
    endif
    EOF
fi

echo endif >> ${LCG_ENV_LOC}/lcgenenv.csh
##### csh #####

chmod a+rx ${LCG_ENV_LOC}/lcgenenv.csh
```



```
chmod a+rx ${LCG_ENV_LOC}/lcfgenv.sh
```

```
return 0
}
```

19.9. CONFIG_REPLICA_MANAGER

```
config_replica_manager(){
```

```
# SE_HOST and CE_HOST are not strictly required
requires BDII_HOST
```

```
se_host="${SE_LIST%% *}"
```

```
INSTALL_ROOT=${INSTALL_ROOT:-/opt}
```

```
if [ -f ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local ]; then
    mv -f ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local /tmp/edg-replica-ma
fi
```

```
cat <<EOF > ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local
@EDG.LOCATION@|${INSTALL_ROOT}/edg|location of edg middleware
@LOCALDOMAIN@|`hostname -d`|the local domain
@DEFAULT.SE@|${se_host}|the host of the close SE
@DEFAULT.CE@|${CE_HOST}|the host of the close CE
@INFOSERVICE@|MDS|The info provider to use. It can be Stub, MDS or RGMA
@RLS.MODE@|lrcOnly|The mode the RLS should be run in. lrcOnly or WithRli
@STUBFILE@||The properties file for the static file - only needed in Stub mode
@MDS.HOST@|${BDII_HOST}|The host of the MDS info provider
@MDS.PORT@|2170|The port of the MDS info provider
@ROS.FAILURE@|false|Fail if no ROS is available
@CONF.GCC@|_gcc3_2_2|The gcc suffix as used on the build box (empty for 2.95, _gcc3_2_2 for 3.2.)
@IGNORE.PREFIX@|true|Whether the RM will ignore the lfn and guid prefix.
@GRIDFTP.DCAU@|false|Does GridFTP use Data Channel Authentication (DCAU)
@GRIDFTP.STREAMS.SMALL@|1|The default number of stream to use for a small file
@GRIDFTP.STREAMS.BIG@|3|The default number of stream to use for a big file
@GRIDFTP.FILESIZE.THRESHOLD@|100|The Threshold (in MB) above which a file to transfer is considered "big"
EOF
```

```
oldEDG_LOCATION=${EDG_LOCATION}
oldEDG_LOCATION_VAR=${EDG_LOCATION_VAR}
export EDG_LOCATION=${INSTALL_ROOT}/edg
export EDG_LOCATION_VAR=${INSTALL_ROOT}/edg/var
```

```
${INSTALL_ROOT}/edg/sbin/edg-replica-manager-configure \
${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local >> $YAIM_LOG
```

```
export EDG_LOCATION=${oldEDG_LOCATION}
export EDG_LOCATION_VAR=${oldEDG_LOCATION_VAR}
```

```
return 0
}
```



19.10. CONFIG_JAVA

```
function config_java () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

# If JAVA_LOCATION is not set by the admin, take a guess
if [ -z "$JAVA_LOCATION" ]; then
    java=`rpm -qa | grep j2sdk-` || java=`rpm -qa | grep j2re`
    if [ "$java" ]; then
JAVA_LOCATION=`rpm -ql $java | egrep '/bin/java$' | sort | head -1 | sed 's#/bin/java##'`
    fi
fi

if [ ! "$JAVA_LOCATION" -o ! -d "$JAVA_LOCATION" ]; then
    echo "Please check your value for JAVA_LOCATION"
    return 1
fi

if ( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then

# We're configuring a relocatable distro

    if [ ! -d ${INSTALL_ROOT}/edg/etc/profile.d ]; then
mkdir -p ${INSTALL_ROOT}/edg/etc/profile.d/
    fi

    cat > $INSTALL_ROOT/edg/etc/profile.d/j2.sh <<EOF

JAVA_HOME=$JAVA_LOCATION
export JAVA_HOME
EOF

    cat > $INSTALL_ROOT/edg/etc/profile.d/j2.csh <<EOF

setenv JAVA_HOME $JAVA_LOCATION
EOF

    chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.sh
    chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.csh

    return 0

fi # end of relocatable stuff

# We're root and it's not a relocatable

if [ ! -d /etc/java ]; then
    mkdir /etc/java
fi

echo "export JAVA_HOME=$JAVA_LOCATION" > /etc/java/java.conf
echo "export JAVA_HOME=$JAVA_LOCATION" > /etc/java.conf
chmod +x /etc/java/java.conf
```




#This hack is here due to SL and the java profile rpms, Laurence Field

```
if [ ! -d ${INSTALL_ROOT}/edg/etc/profile.d ]; then
    mkdir -p ${INSTALL_ROOT}/edg/etc/profile.d/
fi
```

```
cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/j2.sh
if [ -z "$PATH" ]; then
    export PATH=${JAVA_LOCATION}/bin
else
    export PATH=${JAVA_LOCATION}/bin:${PATH}
fi
EOF
```

```
chmod a+rx ${INSTALL_ROOT}/edg/etc/profile.d/j2.sh
```

```
cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/j2.csh
if ( \${?PATH} ) then
    setenv PATH ${JAVA_LOCATION}/bin:${PATH}
else
    setenv PATH ${JAVA_LOCATION}/bin
endif
EOF
```

```
chmod a+rx ${INSTALL_ROOT}/edg/etc/profile.d/j2.csh
```

```
return 0
```

```
}
```

19.11. CONFIG_RGMA_CLIENT

```
config_rgma_client(){
```

```
requires MON_HOST REG_HOST
```

```
INSTALL_ROOT=${INSTALL_ROOT:-/opt}
```

```
# NB java stuff now in config_java, which must be run before
```

```
export RGMA_HOME=${INSTALL_ROOT}/glite
```

```
# in order to use python from userdeps.tgz we need to source the env
```

```
if ( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then
```

```
    . ${INSTALL_ROOT}/etc/profile.d/grid_env.sh
```

```
fi
```

```
${RGMA_HOME}/share/rgma/scripts/rgma-setup.py --secure=yes --server=${MON_HOST} --registry=${REG_HOST} --schema=${R
```

```
cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.sh
```

```
export RGMA_HOME=${INSTALL_ROOT}/glite
```



```
export APEL_HOME=${INSTALL_ROOT}/glite

echo \${PYTHONPATH} | grep -q ${INSTALL_ROOT}/glite/lib/python && isthere=1 || isthere=0
if [ \${isthere} = 0 ]; then
    if [ -z \${PYTHONPATH} ]; then
        export PYTHONPATH=${INSTALL_ROOT}/glite/lib/python
    else
        export PYTHONPATH=\${PYTHONPATH}:${INSTALL_ROOT}/glite/lib/python
    fi
fi

echo \${LD_LIBRARY_PATH} | grep -q ${INSTALL_ROOT}/glite/lib && isthere=1 || isthere=0
if [ \${isthere} = 0 ]; then
    if [ -z \${LD_LIBRARY_PATH} ]; then
        export LD_LIBRARY_PATH=${INSTALL_ROOT}/glite/lib
    else
        export LD_LIBRARY_PATH=\${LD_LIBRARY_PATH}:${INSTALL_ROOT}/glite/lib
    fi
fi
EOF

chmod a+rx ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.sh

cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.csh
setenv RGMA_HOME ${INSTALL_ROOT}/glite
setenv APEL_HOME ${INSTALL_ROOT}/glite

echo \${PYTHONPATH} | grep -q ${INSTALL_ROOT}/glite/lib/python && set isthere=1 || set isthere=0
if ( \${isthere} == 0 ) then
    if ( -z \${PYTHONPATH} ) then
        setenv PYTHONPATH ${INSTALL_ROOT}/glite/lib/python
    else
        setenv PYTHONPATH \${PYTHONPATH}\:${INSTALL_ROOT}/glite/lib/python
    endif
endif

echo \${LD_LIBRARY_PATH} | grep -q ${INSTALL_ROOT}/glite/lib && set isthere=1 || set isthere=0
if ( \${isthere} == 0 ) then
    if ( -z \${LD_LIBRARY_PATH} ) then
        setenv LD_LIBRARY_PATH ${INSTALL_ROOT}/glite/lib
    else
        setenv LD_LIBRARY_PATH \${LD_LIBRARY_PATH}\:${INSTALL_ROOT}/glite/lib
    endif
endif
EOF

chmod a+rx ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.csh

return 0
}
```



19.12. CONFIG_WORKLOAD_MANAGER_CLIENT

```
function config_workload_manager_client() {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if [ $UID -eq 0 ]; then
    OUTPUT_STORAGE=${OUTPUT_STORAGE:-/tmp/jobOutput}
else
    OUTPUT_STORAGE=${OUTPUT_STORAGE:-${HOME}/jobOutput}
fi

requires PX_HOST RB_HOST VOS

for i in $VOS ; do
if [ ! -d $INSTALL_ROOT/edg/etc/$i ]; then
mkdir -p $INSTALL_ROOT/edg/etc/$i
fi
if [ -f $INSTALL_ROOT/edg/etc/$i/edg_wl_ui.conf ]; then
mv -f $INSTALL_ROOT/edg/etc/$i/edg_wl_ui.conf /tmp/edg_wl_ui.conf.$i.orig
fi
cat <<EOF >$INSTALL_ROOT/edg/etc/$i/edg_wl_ui.conf
[
VirtualOrganisation = "$i";
NSAddresses = "$RB_HOST:7772";
LBAddresses = "$RB_HOST:9000";
## HLR location is optional. Uncomment and fill correctly for
## enabling accounting
##HLRLocation = "fake HLR Location"
## MyProxyServer is optional. Uncomment and fill correctly for
## enabling proxy renewal. This field should be set equal to
## MYPROXY_SERVER environment variable
MyProxyServer = "$PX_HOST"
]
EOF
done

if [ -f $INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf ]; then
mv -f $INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf /tmp/edg_wl_ui_cmd_var.conf.orig
fi
cat <<EOF >$INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf
[
rank = - other.GlueCEStateEstimatedResponseTime;
requirements = other.GlueCEStateStatus == "Production";
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "${OUTPUT_STORAGE}";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "$RB_HOST:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)

```



```
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
EOF

if [ -f $INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf ]; then
mv -f $INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf /tmp/edg_wl_ui_gui_var.conf.orig
fi
cat <<EOF >$INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf
[
JDLEDefaultSchema = "Glue";
Glue = [
rank = - other.GlueCEStateEstimatedResponseTime;
rankMPI = other.GlueCEStateFreeCPUs;
requirements = other.GlueCEStateStatus == "Production"
];
EDG = [
rank = - other.EstimatedTraversalTime;
rankMPI = other.FreeCPUs;
requirements = true
];
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "$OUTPUT_STORAGE";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "$RB_HOST:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
EOF

if [ ! -d $OUTPUT_STORAGE ]; then
mkdir $OUTPUT_STORAGE
fi

if [ $UID -eq 0 ]; then
chmod 1777 $OUTPUT_STORAGE
fi

if [ ! -d ${INSTALL_ROOT}/edg/var/etc/profile.d ]; then
mkdir -p ${INSTALL_ROOT}/edg/var/etc/profile.d
fi

for i in edg-wl-ui-env.csh edg-wl-ui-env.sh edg-wl-ui-gui-env.csh edg-wl-ui-gui-env.sh; do
if [ -f ${INSTALL_ROOT}/edg/etc/profile.d/${i} ]; then
```



```
cp -f ${INSTALL_ROOT}/edg/etc/profile.d/${i} ${INSTALL_ROOT}/edg/var/etc/profile.d
fi
done

}
```

19.13. CONFIG_VOMSES

```
function config_vomses () {

requires VOS

if [ $UID -eq 0 ]; then
    vomsespath="${INSTALL_ROOT}/edg/etc/vomses"
else
    vomsespath="$HOME/.edg/vomses"
fi

if [ "$vomsespath" -a ! -d "$vomsespath" ]; then
    mkdir -p $vomsespath
fi

for vo in $VOS; do
    eval vomses='${VO}_`echo $vo | tr '[:lower:]' '[:upper:]'`_VOMSES'
    if [ -z "$vomses" ]; then continue; fi
    split_quoted_variable $vomses | while read line; do
server=`echo $line | awk '{print $2}'`
filename="${vo}-${server}"
echo $line | sed -e 's/ /" "/g' -e 's/^"/' -e 's/$"/' > $vomsespath/$filename
chmod 644 $vomsespath/$filename
    done
done

if [ $UID -eq 0 ]; then
    if [ ! -d $INSTALL_ROOT/glite/etc/vomses ]; then
mkdir -p $INSTALL_ROOT/glite/etc/vomses
    fi
    cp -p $vomsespath/* $INSTALL_ROOT/glite/etc/vomses
fi

return 0

}
```

19.14. CONFIG_FTS_CLIENT

```
function config_fts_client () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if [ -z "$FTS_SERVER_URL" ]; then
```



```
    return 0
fi

cat > ${INSTALL_ROOT}/glite/etc/services.xml <<EOF
<?xml version="1.0" encoding="UTF-8"?>

<services>

  <service name="EGEEfts">
    <parameters>
      <endpoint>${FTS_SERVER_URL}/services/FileTransfer</endpoint>
      <type>org.glite.FileTransfer</type>
      <version>3.0.0</version>
    </parameters>
  </service>

  <service name="EGEEchannel">
    <parameters>
      <endpoint>${FTS_SERVER_URL}/services/ChannelManagement</endpoint>
      <type>org.glite.ChannelManagement</type>
      <version>3.0.0</version>
    </parameters>
  </service>

</services>
EOF

return 0

}
```

19.15. CONFIG_GLITE_ENV

```
function config_glite_env () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

cat > /etc/profile.d/gliteenv.sh <<'EOF'

if test "x${LCG_ENV_SET+x}" = x; then

  GLITE_LOCATION=${GLITE_LOCATION:-/opt/glite}
  GLITE_LOCATION_VAR=${GLITE_LOCATION_VAR:-$GLITE_LOCATION/var}
  GLITE_LOCATION_LOG=${GLITE_LOCATION_LOG:-$GLITE_LOCATION/log}
  GLITE_LOCATION_TMP=${GLITE_LOCATION_TMP:-$GLITE_LOCATION/tmp}

  if [ -z "$PATH" ]; then
PATH=${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
  else
PATH=${PATH}:${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
  fi
fi
```



```
    if [ -z "$LD_LIBRARY_PATH" ]; then
LD_LIBRARY_PATH="${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    else
LD_LIBRARY_PATH="${LD_LIBRARY_PATH}:${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    fi

    if [ -z "$PERLLIB" ]; then
PERLLIB="${GLITE_LOCATION}/lib/perl5"
    else
PERLLIB="${PERLLIB}:${GLITE_LOCATION}/lib/perl5"
    fi

    if [ -z "$MANPATH" ]; then
MANPATH="${GLITE_LOCATION}/share/man"
    else
MANPATH="${MANPATH}:${GLITE_LOCATION}/share/man"
    fi

    export GLITE_LOCATION GLITE_LOCATION_VAR GLITE_LOCATION_LOG GLITE_LOCATION_TMP PATH LD_LIBRARY_PATH PERLLIB MANPATH

fi

EOF

cat > /etc/profile.d/gliteenv.csh <<'EOF'

if ( ! $?LCG_ENV_SET ) then

    if ( ! $?GLITE_LOCATION ) then
setenv GLITE_LOCATION "/opt/glite"
    endif

    if ( ! $?GLITE_LOCATION_VAR ) then
setenv GLITE_LOCATION_VAR "${GLITE_LOCATION}/var"
    endif

    if ( ! $?GLITE_LOCATION_LOG ) then
setenv GLITE_LOCATION_LOG "${GLITE_LOCATION}/log"
    endif

    if ( ! $?GLITE_LOCATION_TMP ) then
setenv GLITE_LOCATION_TMP "${GLITE_LOCATION}/tmp"
    endif

    if ( ! $?PATH ) then
setenv PATH "${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
    else
setenv PATH "${PATH}:${GLITE_LOCATION}/bin:${GLITE_LOCATION}/externals/bin"
    endif

    if ( ! $?LD_LIBRARY_PATH ) then
setenv LD_LIBRARY_PATH "${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    else
setenv LD_LIBRARY_PATH "${LD_LIBRARY_PATH}:${GLITE_LOCATION}/lib:${GLITE_LOCATION}/externals/lib"
    fi
fi
```



```
endif

if ( ! $?PERLLIB ) then
setenv PERLLIB "${GLITE_LOCATION}/lib/perl5"
else
setenv PERLLIB "${PERLLIB}:${GLITE_LOCATION}/lib/perl5"
endif

if ( ! $?MANPATH ) then
setenv MANPATH "${GLITE_LOCATION}/share/man"
else
setenv MANPATH "${MANPATH}:${GLITE_LOCATION}/share/man"
endif

endif

EOF

return 0

}
```

19.16. CONFIG_GSISSH

```
config_gsissh(){

INSTALL_ROOT=${INSTALL_ROOT:-/opt}
export GLOBUS_LOCATION=${INSTALL_ROOT}/globus
export PERLLIB=${PERLLIB}:${INSTALL_ROOT}/gpt/lib/perl

#configuring gsissh server

if [ -f ${INSTALL_ROOT}/globus/setup/gsi_openssh_setup/setup-openssh ]; then
    ${INSTALL_ROOT}/globus/setup/gsi_openssh_setup/setup-openssh
else
    echo "Impossible to configure gsissh: setup-openssh configuration script not found"
    exit 1
fi

if ( echo "${NODE_TYPE_LIST}" | grep VOBOX > /dev/null ); then

requires VOBOX_PORT

cat ${INSTALL_ROOT}/globus/sbin/SXXsshd | sed "s/SSHD_ARGS=\"\"/SSHD_ARGS=\"-p ${VOBOX_PORT}\"/" > ${INSTALL_ROOT}/

if [ $? == 0 ]; then
    mv ${INSTALL_ROOT}/globus/sbin/SXXsshd.TMP ${INSTALL_ROOT}/globus/sbin/SXXsshd
    chmod +x ${INSTALL_ROOT}/globus/sbin/SXXsshd
else
    echo "Unable to modify GSISSH startup script."
    exit 1
fi
}
```




```
fi

if [ "x`grep LCG ${INSTALL_ROOT}/globus/etc/ssh/sshd_config`" = "x" ]; then
cat <<EOF >>${INSTALL_ROOT}/globus/etc/ssh/sshd_config
#####
#ADDs ON from LCG

PermitRootLogin no
RSAAuthentication no
PubkeyAuthentication no
PasswordAuthentication no
ChallengeResponseAuthentication no
#####

EOF

fi

# install the service under /etc/init.d and configure it

if [ ! -f /etc/init.d/gsisshd ]; then
ln -s ${INSTALL_ROOT}/globus/sbin/SXXsshd /etc/init.d/gsisshd
fi

/sbin/chkconfig --add gsisshd
/sbin/chkconfig gsisshd on
/sbin/service gsisshd restart

fi

#configure the client

if [ ! -d ${INSTALL_ROOT}/globus/etc/ssh ]; then
mkdir -p ${INSTALL_ROOT}/globus/etc/ssh
fi

if [ "x`grep LCG ${INSTALL_ROOT}/globus/etc/ssh/ssh_config`" = "x" ]; then

cat <<EOF >>${INSTALL_ROOT}/globus/etc/ssh/ssh_config
#####
#ADDs ON from LCG

GssapiAuthentication yes
GssapiKeyExchange yes
GssapiDelegateCredentials yes

#####
EOF
```



fi

}